

Backing-up and Upgrading

Backing-up

To successfully backup the database:

Ensure all users are logged out of Invu.

Terminate all of the Invu services, starting with the database services and concluding with the Centura SQLBase service.

Backup the S200 or S250 subfolder located in the Centura directory. (i.e. the closed dbs file and any existing log files)

Backup the File Repository (FR)

NB. It is strongly recommended that the backup is performed on a closed file, i.e. the Database Engine is stopped.

Restoring

- I. Terminate the Services
- II. Replace the S200/S250 folder with the backup copy (any log files that existed at the time of backup must be available when restoring the database)
- III. Replace the FR if required
- IV. Restart the services, starting with the Centura SQL Base service.